

SubscribeMonitoredItem	Action, Create EasyUAClient; Call _EasyUAClient....	
SubscribeMonitoredItem	Action, Call _EasyUAClient.SubscribeMonitoredItem	
SubscribeMonitoredItem	Action, Call _EasyUAClient.SubscribeMonitoredItem	
Wait	TimeInterval(2)	
For	Locals.Loops = 0; Locals.Loops < 1000; Locals.Lo...	
ReadValue	Action, Call _EasyUAClient.ReadValue	
Read	Action, Call _EasyUAClient.Read	
ReadValue - LocalizedText	Action, Call _EasyUAClient.ReadValue	
Read - LocalizedText	Action, Call _EasyUAClient.Read	
End		
WriteValue	Action, Call _EasyUAClient.WriteValue	
UnsubscribeMonitoredItem	Action, Call _EasyUAClient.UnsubscribeMonitored...	Skip
UnsubscribeAllMonitored	Action, Call _EasyUAClient.UnsubscribeAllMonitor...	

Step Settings for SubscribeMonitoredItem

Automation Server: OPC Labs EasyOPC-UA Library (Ver 5.21)

Object Reference: Locals.ObjectReference

Object Class: EasyUAClient (_EasyUAClient)

Call Method: SubscribeMonitoredItem

Parameter Name	Type	Direction	Log	Default	Value
Return Value	Number (Signed 32-bit Integer)	out	<input type="checkbox"/>		Locals.Handle
endpointDescriptorString	String	in	<input type="checkbox"/>		"opc.tcp://192.168.1.213:4880/Pliz/PvisOpcUAServer/None"
nodeDescriptorString	String	in	<input type="checkbox"/>		"ns=2,s=OPC/PSS3000-Dauertest/Generic/ST/DB/20/DW/0"
samplingInterval	Number (Signed 32-bit Integer)	in	<input type="checkbox"/>		1000

STOP

SubscribeMonitoredItem	BrowseDataNodes
SubscribeMonitoredItem	BrowseDataVariables
SubscribeMonitoredItem	BrowseMethods
SubscribeMonitoredItem	BrowseNodes
Wait	BrowseObjects
For	BrowseProperties
ReadValue	BrowseVariables
Read	CallMethod
ReadValue - LocalizedText	CallMultipleMethods
Read - LocalizedText	ChangeMonitoredItemSubscription
End	ChangeMultipleMonitoredItemSubscriptions
WriteValue	DiscoverApplications
UnsubscribeMonitoredItem	DiscoverServers
UnsubscribeAllMonitored	Equals
Anforderungen UA Client	FindApplications
Message Security Mode	GetHashCode
LocaleID	GetMonitoredItemArguments
	GetMonitoredItemArgumentsDictionary
	GetType
	Read
	ReadMultiple
	ReadMultipleValues
	ReadValue
	SubscribeMonitoredItem
	SubscribeMultipleMonitoredItems
	UnsubscribeAllMonitoredItems
	UnsubscribeMonitoredItem
	UnsubscribeMultipleMonitoredItems
	Write
	WriteMultiple
	WriteMultipleValues
	WriteValue

Step Settings for SubscribeMonitoredItem

Automation Server:

Object Reference:

Object Class:

Call Method: SubscribeMonitoredItem

Parameter Name	Type
Return Value	Number (Signed 32-bit Integer)